

How to stop and start services

Stopping and starting GroundWork Monitor services



In most cases, stopping, starting, and restarting any of the services is not advised. These services are interdependent upon one another. Restarting `gwservices` or other GroundWork Monitor services may make UI components unresponsive in the browser. If you must stop and start one of these services have all users log out of the server first.

Stop, Start, Restart, Status Services

- Apache2

```
service groundwork stop apache
```

```
service groundwork start apache
```

```
service groundwork restart apache
```

```
service groundwork status apache
```

- SNMP Trap Translator

```
service groundwork stop snmptt
```

```
service groundwork start snmptt
```

```
service groundwork restart snmptt
```

```
service groundwork status snmptt
```

- SNMP Trap Daemon

```
service groundwork stop snmptrapd
```

```
service groundwork start snmptrapd
```

```
service groundwork restart snmptrapd
```

```
service groundwork status snmptrapd
```

- Nagios

```
service groundwork stop nagios
```

```
service groundwork start nagios
```

```
service groundwork restart nagios
```

```
service groundwork status nagios
```

- Foundation

```
service groundwork stop gwservices
```

```
service groundwork start gwservices
```

```
service groundwork restart gwservices
```

```
service groundwork status gwservices
```

- syslog-ng

```
service groundwork stop syslog-ng
```

```
service groundwork start syslog-ng
```

```
service groundwork restart syslog-ng
```

```
service groundwork status syslog-ng
```

- syslogd

```
service groundwork stop syslogd
```

```
service groundwork start syslogd
```

```
service groundwork restart syslogd
```

- PostgreSQL

```
service groundwork stop postgresql
```

```
service groundwork start postgresql
```

```
service groundwork restart postgresql
```

```
service groundwork status postgresql
```

Stop, Start, Restart, Status Agents

GDMA

- AIX

```
startsrc -s gdma
```

```
stopsrc -s gdma
```

```
lssrc -s gdma
```

- Linux

```
service gdma start
```

```
service gdma stop
```

```
service gdma restart
```

```
service gdma status
```

- Solaris

```
/etc/init.d/gdma start
```

```
/etc/init.d/gdma stop
```

```
/etc/init.d/gdma status (GDMA 2.5.0 and later)
```

- Windows

```
net start gdma
```

```
net stop gdma
```

Stop, Start, Restart Applications

- Notification Manager (NoMa)

```
service groundwork stop noma
```

```
service groundwork start noma
```

```
service groundwork restart noma
```

```
service groundwork status noma
```

- Ntop

```
service groundwork stop ntop
```

```
service groundwork start ntop
```

```
service groundwork restart ntop
```

```
service groundwork status ntop
```